

Description: Guide to the ICONICS Web Licensing Utility for Software License.

OS Requirement: Win 2000 Pro/Server, XP Pro, Server 2003.

Internet Browser: Internet Explorer 6.0 and higher.

General Requirement: Internet Browser (IE 6), GENESIS32 or BizViz (any version).

Issue a new Software License

1. On the machine where you want the GENESIS32 license to reside, open the License Utility by going to Start → Programs → ICONICS Software Licensing.
2. Once the License Utility opens, go to Actions → Authorize License.
3. You will see a dialog come up with a Site Code and a blank for a Site Key as show in figure below. Leave this window open.



Figure 1

4. Go to <http://www.iconics.com/supportworx>, launch the Web Licensing Utility Site by clicking on *License Your Product*.



Figure 2

5. The Home page of the Web Licensing Utility Site will be loaded. Select the Software License Icon to access the Software License Options.



Figure 3

6. You will be required to log in to access the Software License Options. Insert your email address and password and click *Login*.



Figure 4

7. Once you have logged into the website, click on the “New License” link in the top navigation bar.
8. Enter your Product Registration Numbers and Customer Keys for the products to License. Click *Next*.

Licensing – Using the ICONICS Web Licensing Utility for Software License

APPLICATIONS NOTE

February 2008

Figure 5

NOTE: Your Customer Key and Product Registration Number are usually on the back of the original CD that ICONICS sent to you.

- In the next screen it is requested to identify the end user for whom the license is being issued. You can look up a list of already inserted end users or insert a new one by clicking the *Existing End Users* link or clicking the *Create New* link respectively.

Figure 6

- Clicking the Existing End User link, will open a new window with a list of already inserted end users previously entered by you or tied to the product registrations numbers entered in the previous screen. Select an end user from the list and click *Select* or double click the selected end user. If you are the end user and you are not listed in the grid, you can click on *I am the End User* to insert your data as the new end user. After identifying the end user, click *Next*.

Figure 7

- In the next screen, you will see a list of the products that are available for you to license; check all the products that you would like to license. Copy the Site Code from the license utility of the destination station and paste it into the Site Code text box of the current web page. Click *Next*.

Select	Product Key	Product Description	RegNo
☒	B2VZ-SP V8 C12	12 MONTH CONSIGNMENT LICENSE FOR V8 B2VZ	G79565919
☐	B2VZ-SP V8 C12	12 MONTH CONSIGNMENT LICENSE FOR V8 B2VZ	G79565919
☐	B2VZ-SP V8 C12	12 MONTH CONSIGNMENT LICENSE FOR V8 B2VZ	G79565919
☐	B2VZ-SP V8 C12	12 MONTH CONSIGNMENT LICENSE FOR V8 B2VZ	G79565919
☐	GENES032-SP V7 C12	12 MONTH CONSIGNMENT LICENSE FOR SP	G79565919
☐	GENES032-SP V8 C12	12 MONTH CONSIGNMENT LICENSE FOR V8	G79565919
☐	GENES032-SP V9 C12	12 MONTH CONSIGNMENT LICENSE FOR V9	G79565919
☐	GENES032-SP V9 C12	12 MONTH CONSIGNMENT LICENSE FOR V9	G79565919
☐	GENES032-SP V9 C12	12 MONTH CONSIGNMENT LICENSE FOR V9	G79565919

Figure 8

- Review the license information before proceeding. Click *Generate Site Key* to issue the new site key.

Product Key	Product Description	RegNo	ICUs
B2VZ-SP V8 C12	12 MONTH CONSIGNMENT LICENSE FOR V8 B2VZ	G79565919	210

Figure 9

- The next page will show you a summary of what will be in your license.

Licensing – Using the ICONICS Web Licensing Utility for Software License

APPLICATIONS NOTE

February 2008




Figure 10

- Copy and paste the generated Site Key into your License Utility in your PC and click on the Update Button.
- You should now have a license when you go to Actions → View License.

Adding To Existing Software License

Go to <http://www.iconics.com/supportworx>, launch the Web Licensing Utility Site by clicking on *License Your Product*. (See Figure 2).

- Once you have logged into the website and accessed the Software License Home Page, click on the *Add to License* link on the top menu bar.
- Enter your Current Site Key, Customer Codes, and Product Registration Numbers. Click *Next*.




Figure 11

- In the next screen, you will see a summary of the current license and a list of the products that are available for you

to add to the existing license. Check all the products that you would like to license. Copy the Site Code from the license utility of the destination station and paste it into the Site Code text box of the current web page. Click *Next*.



Figure 12

- Review the license information before proceeding. Select *Generate Site Key* as shown in the figure below.




Figure 13

- The next screen will display the new site key.

Licensing – Using the ICONICS Web Licensing Utility for Software License

APPLICATIONS NOTE

February 2008




Figure 14

- Enter the Site key into the Iconics License Utility for License activation.

Killing a Software License

Go to <http://www.iconics.com/supportworx> launch the Web Licensing Utility Site by clicking on *License Your Product*. (See Figure 2).

- Once you have logged into the website and accessed the Software License Home Page, click on the *Kill License* link on the top menu bar.
- Open your License Utility on your source machine by going To Start → Programs → ICONICS Software Licensing.
- Once the License Utility is opened, go to Actions → Kill License.
- It will then ask you for a user name and password as seen in figure below. Enter your name and the password: "itisok" (without quotes).




Figure 15

- Copy the Site Key in to the Site Key field on the webpage and the Kill Confirmation Code into the Kill Code field on the webpage and select Remove Key button in the webpage.



Figure 16

- You will get a message confirming that the Site Key has been successfully deleted as shown in the figure below. The products associated with the deleted Site Key will be available to be re -licensed.



Figure 17